

## **G5 Series**

# **Regatron G5**

***LabVIEW Rest API Access***

**Regatron AG**  
Feldmühlestrasse 50  
CH-9400 Rorschach  
Tel +41 71 846 67 44  
Fax +41 71 846 67 77  
[www.regatron.com](http://www.regatron.com)  
[support@regatron.com](mailto:support@regatron.com)

## **Getting Started**

**Version V 1.0**

© 2010- 2021 Regatron AG

This document is protected by copyright.

All rights, including translation, re-printing and duplication of this manual or parts of it, reserved. No part of this document is allowed to be reproduced or processed using electronic systems, copied or distributed in any form (by photocopying, microfilming or any other process), also not for educational purposes, without the written approval of Regatron AG.

This information in this documentation corresponds to the development situation at the time of going to print and is therefore not of a binding nature. Regatron AG reserves the right to make changes at any time for the purpose of technical progress or product improvement, without stating the reasons. In general we refer to the applicable issue of our "Terms of delivery".

LabVIEW is registered trademark of National Instruments, USA.  
Windows is registered trademark of Microsoft Inc., USA.

Overview of versions	
<b>Operating instructions / programming handbook</b>	Version V 1.0

All information is subject to technical changes without prior notice.

# Content

<b>Content .....</b>	<b>3</b>
<b>1. Overview .....</b>	<b>4</b>
1.1. Content .....	4
1.2. Precondition / Dependencies .....	4
<b>2. LabVIEW Access .....</b>	<b>5</b>
2.1. VI Files .....	5
2.2. Need components .....	5
2.3. General Recommendations .....	6
2.3.1. Basic Init VI .....	6
2.3.2. Configuration (..\Settings) .....	6
2.3.3. References (..\Power) .....	6
2.3.4. Output Values (..\Power) .....	6
2.3.5. System Info (..\Info) .....	7
2.3.6. Utility (..\Info) .....	7
2.3.7. Func Generator (..\F-Generator) .....	7
2.3.8. Examples (..\Example) .....	8
<b>3. Change log .....</b>	<b>9</b>

## 1. Overview

The TopCon LabVIEW API can be used to access the Regatron G5 HMI to perform a small set of operations.

It cannot substitute the G5Control PC Software, but offers some methods to automate certain operations.

The main configuration and error analysis can only be done with the TopControl software.

### 1.1. Content

This document provides a guideline how to access the G5 LabVIEW VI's.

### 1.2. Precondition / Dependencies

To be able to use the G5 LabVIEW API the G5Control software must not be installed on the system.

For more Information read the Software Manual witch you can found in the G5Control software menu -> Help.


## 2. LabVIEW Access

There is a LabVIEW VI library to access the TC and GSS Devices.

3 Examples are delivered and can help to get your first LabVIEW program running.

You can get an overview with the VI tree “Regatron.G5.Rest VI Tree.vi” in the main directory.

### 2.1. VI Files



### 2.2. Need components

The G5 VIs are based on the free "JKI http TEST Client" library.



Please download this library via the JKI VI Package Manager.

## 2.3. General Recommendations


To access the API from LabVIEW, there are some points to mention.

### 2.3.1. Basic Init VI

G5.Rest INIT Ethernet.vi:

The connection can only be established to a HMI.

It supports the connection to multiple HMI.



TC CLOSE: Disconnect the device



### 2.3.2. Configuration (..\Settings)

TC Slopes: Slopes Ramp Setting (Read/Write)



TC Protect Values: Protect Setting (Read/Write)



### 2.3.3. References (..\Power)

TC Power ONOFF: Voltage ON/OFF Setting (Read/Write)




TC Power References: Preset and Limit Setting (Read/Write)



Datasource:

Read or Write Power Setting with Datasource

It is not necessary to write all values.



### 2.3.4. Output Values (..\Power)

TC Power Values: Output Values (Read)



### 2.3.5. System Info (..\Info)

TC Device Info: Modul Typ, Serial Nr., Modul ID, GSS



TC Device Software Info: Firmware Versions, SW Options



TC Device Info System: Nominal Modul and Multi Modul Values



TC Device State: State of the TC (Warning, Error, Run)



### 2.3.6. Utility (..\Info)

TC Clear Error: Clear TC Modul or System



TC Store Settings: Store Settings to Flash



TC Sense Settings: Sense Settings



### 2.3.7. Func Generator (..\F-Generator)

TC FGenerator Base: Set Basic Values for the Frequency



TC FGenerator User defined: Point Frequency Values



### 2.3.8. Examples (..\Example)

3 LabVIEW test Examples are provided to show how to access the G5 Rest API.

The examples are for LabVIEW 2015 and LabVIEW 2021.

#### Example G5 Control



VI Tree: Regatron.G5.Rest VoltageSample.vi



### 3. Change log

This change log contains a list of changes in the previous versions of the documentation

Version	Date	Changes in documentation
1.00	2021-11-25	Initial documentation



Address: Feldmühlestrasse 50  
CH-9400 Rorschach  
WWW: [www.regatron.com](http://www.regatron.com)  
Email: [support@regatron.com](mailto:support@regatron.com)

Tel: +41 71 846 67 44  
Fax: +41 71 846 67 77